

Drafting with Weaving Software

Enter Data

◆ Enter Data

- Threading, treading, tie-up, dents, and color.


Questions:

- ◆ Insert/ Delete keys will insert/delete ends, picks, treadles. (Yes/No)
- ◆ Blank ends, picks, and treadles are allowed. (Yes/No)

Patternland Enter Data

- a. Smart Cursor/Keyboard
- b. Cursor Keys and Spacebar
- c. Click and Drag
- d. Color
- e. Symbols
- f. Thickness
- g. Copy or Repeat
- h. Add Tabby

Insert/Delete OK
Blanks OK



Patternland

a. Smart Cursor/Keyboard

Smart Cursor/Keyboard


Ctrl s toggles the smart cursor; a cursor key sets the direction of movement, right, left, up, down. Once the smart cursor is on and the direction is set, keyboard input can be used. The visual mnemonic mapping allows entry up to 40. (4 is shaft 4, r is 14, f is 24, v is 34.)

Colors are input with Caps Lock on.

Symbols are input with Scroll Lock on.

The number pad can also be used for

Shafts/treadles up to 99.



Patternland

b. Cursor Keys and Spacebar

Cursor Keys and Spacebar

Using the smart cursor (Ctrl s) and the numeric pad corner keys to set diagonal direction, holding down the spacebar will enter a straight draw. Diagonal direction can be switched by using Ctrl spacebar.

				6				6			6			
			5				5				5			
		4					4				4			
	3					3					3			
	▲				2			2			2			
					1			1	1					1

Patternland

c. Click and Drag


Click and Drag

Using the mouse to click and drag enters data in the squares the mouse cursor touches. Draws freehand curves.

					6					
			5	5		5	5			
	4	4						4	4	
3									3	
										2
										1

Patternland d. Color

Color



Color Brush

Using the color brush and color bar, click on end/pick to input color in grids or drawdown

Format → Styles →

Threading and Tieup: Numeric

Treadling: Graphic/Palette

Warp/Weft: Graphic/Palette

Color Bar

Patternland e. User Symbols

Symbol Brush

Warp Bar


Format → Styles →

Threading: Symbol

Tieup: Numeric

Treading: Graphic/Palette

Warp/Weft: Graphic/Palette



Patternland f. Thickness

Using the warp/weft bars and change the numeric symbols for each thick thread. Turn on Variable Size for the size and shape set.

View in Display or Print Preview

